

Connecting a Model PEL 102/103/105 to DataView®



ENGLISH

Tutorial



Copyright

Copyright © Chauvin Arnoux®, Inc. d.b.a. AEMC® Instruments. All rights reserved.

No part of this documentation may be reproduced in any form or by any means (including electronic storage and retrieval or translation into any other language) without prior agreement and written consent from Chauvin Arnoux®, Inc., as governed by United States and International copyright laws.

Chauvin Arnoux®, Inc. d.b.a. AEMC® Instruments
15 Faraday Drive, Dover, NH 03820 USA
Tel: (800) 945-2362 or (603) 749-6434, Fax: (603) 742-2346

This documentation is provided “as is,” without warranty of any kind, expressed, implied, or otherwise. Chauvin Arnoux®, Inc. has made every reasonable effort to ensure that this documentation is accurate; but does not warrant the accuracy or completeness of the text, graphics, or other information contained in this documentation. Chauvin Arnoux®, Inc. shall not be liable for any damages, special, indirect, incidental, or inconsequential; including (but not limited to) physical, emotional, or monetary damages due to lost revenues or lost profits that may result from the use of this documentation, whether or not the user of the documentation has been advised of the possibility of such damages.

Chauvin Arnoux®, Inc., AEMC®, DataView® & PowerPad® are registered trademarks of AEMC® Instruments.

Contents

Introduction 4

Lesson 1: USB 5

Lesson 2: Bluetooth..... 8

Lesson 3: Ethernet LAN 11

Lesson 4: Ethernet Direct (Point-to-Point, APIPA Mode)..... 14

Lesson 5: Wi-Fi Ethernet 16

Lesson 6: Wi-Fi Direct 20

Lesson 7: IRD Server 23

Contacting AEMC 27

Introduction

Welcome to the tutorial for connecting a Power and Energy Logger Model PEL 100 Series instrument to a computer running the DataView® PEL Control Panel. The PEL Control Panel is designed for working with the Models PEL 102, 103, and 105. These instruments offer a variety of connection options, including:

Connection Type	PEL 102/103	PEL 105
USB	✓	✓
Bluetooth	✓	✓
Ethernet LAN	✓	✓
Ethernet direct, APIPA (Automatic Private IP Addressing) mode		✓
Ethernet Wi-Fi		✓
Wi-Fi direct		✓
IRD (Internet Relay Device) server		✓

This tutorial explains how to set up each of these connection types.


Before You Begin

- This tutorial explains how to use the PEL Control Panel to enabling and disable various communication options. Some of these options can also be enabled/disabled through the instrument's front panel. Consult the user manual that comes with your PEL instrument for instructions on how to do this.
- The tutorial is designed to provide a hands-on experience. As we explain each task, we suggest you follow along using your own instrument and computer. So before you begin, install DataView (version 3.15 or later) with the PEL Control Panel. If you need assistance installing DataView, consult your instrument's user manual.
- For detailed information about using the PEL Control Panel, open the Control Panel and press F1 to open the Help system. (The Help system is context-sensitive and provides specific information about the task you are currently performing.) Another good source of information is the AEMC YouTube channel; see <https://www.youtube.com/user/AEMCinstruments>.
- We encourage you to proceed with this tutorial at your own pace. If there are lessons you'd like to repeat, simply stop the tutorial and go back to the beginning of the lesson. Conversely, feel free to skip any topics with which you are already familiar.
- The instructions and screenshots in this tutorial assume you are running Windows 7. They should also apply to later versions of Windows; although you may encounter some small differences when using these operating systems.
- The steps described in this tutorial were performed with the PEL Model 105. Configuration options may vary slightly with other PEL models.


Lesson 1: USB




1. Connect the PEL to an available USB port on the computer using the supplied USB cable. Provided you have a “default” Windows layout with the taskbar at the bottom of the screen, a popup should appear in the lower right corner indicating that the device driver is installing.




2. Once this driver installation is complete, open the PEL Control Panel by either (a) double clicking the  icon on your desktop, or (b) opening the Start menu and navigating to the PEL Control Panel program located in the DataView folder:



3. To connect to an instrument for the first time either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or (b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.




4. Ensure the **USB** radio button is selected, and then click **Next**. This displays the **Add an Instrument Wizard – USB** dialog box:



5. The **Instrument** field lists any PEL instrument(s) currently connected to the computer via USB. Click the downarrow to display a drop-down list of all available instruments. Select the appropriate PEL and click **Next**.

6. If the connection is successful, the following screen will appear:



Select **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 2: Bluetooth




Bluetooth provides a direct connection similar to USB; however it requires several prerequisite steps.

1. Ensure the computer has Bluetooth capability, either built-in or via a Bluetooth/USB adapter. (The remaining steps in this lesson assume you are using an adapter. Your steps and screens may be different depending on how your computer is configured for Bluetooth.)
2. Ensure Bluetooth is enabled on the PEL, as indicated by the Bluetooth LED on the instrument's front panel.


On the PEL 103 and 105, you can enable Bluetooth through the instrument's front panel interface, as instructed by the instrument's user guide.

On the PEL 102, you must connect the instrument to the computer through a USB connection (see [Lesson 1](#)) and use the Control Panel to enable Bluetooth. (Consult the Control Panel Help for instructions.)


3. You must now pair the instrument to the computer. Click the **Start** button and select **Devices and Printers**.



4. Click **Add a device** on the top left. The computer scans for all Bluetooth devices within the range of its Bluetooth radio. When finished, available devices are listed in the **Add a device** screen.



5. If the PEL to which you want to connect is listed, select it. (You can identify the PEL by its serial number.) Then click **Next** to begin the pairing process.
6. When prompted for a pairing code, enter the default pairing code (0000) and click **Next**.
7. The popup message **Installing device driver** should appear on the lower right of the screen. Clicking the message will open a dialog box that is similar to the following:




NOTE: The driver is not fully installed until there are green checkmarks in the preceding dialog box. Depending on your system, the time the process requires will vary. Once the correct pairing code is entered, the screen will display the message **The device has been successfully added to this computer**. However, communication to the device is still not possible until the Bluetooth drivers are fully installed, and the green checkmarks appear.

8. When the pairing process is complete, open the PEL Control Panel. You can now create a connection to the instrument. The steps for doing this depend on whether or not the instrument is already connected to DataView.

If the instrument is not connected, skip the remainder of this step and go to step 9 below.

If the instrument is already connected, you can either modify the existing connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard, and proceed as instructed in step 10. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.

9. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or (b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.
10. Select the **Bluetooth** radio button and click **Next**. This displays the **Add and Instrument – Bluetooth** dialog box.



11. When this dialog box first opens, the computer builds a list of PEL instruments available for Bluetooth connection. When this process is finished, click the downarrow to display a drop-down list of all available instruments. Select the appropriate PEL and click **Next**.
12. If the connection is successful, a screen appears informing you of this. Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 3: Ethernet LAN



This lesson assumes the PEL instrument to which you want to connect is located on your local network via an Ethernet cable, and the computer is also connected to that network via LAN or Wi-Fi.

To set up an Ethernet LAN connection, you must be connected to the instrument via a USB ([Lesson 1](#)) or Bluetooth ([Lesson 2](#)) connection. Then proceed as follows:

1. Ensure that an Ethernet cable is connected to the network port on the front panel of the instrument, with the other end of the cable connected to an appropriate network jack (wall or router) which has access to the local network.
2. In the PEL Control Panel, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, and click **Configure** (or click the  icon in the toolbar) to display the Configure Instrument dialog box.
3. Open the **Communication** tab.

The screenshot shows the 'Configure' dialog box with the 'Communication' tab selected. The dialog has several sections:


- Bluetooth:** Enable Bluetooth. Pairing code: 0000. Name: PEL 105 -134461NEH (25 ASCII characters max). Visibility: Visible, Invisible.
- Network:** MAC address: 1E:07:80:00:00:07 (Edit button). Enable DHCP. IP address: 10 . 1 . 11 . 40. Subnet mask: 255 . 255 . 255 . 0. Gateway address: 10 . 1 . 11 . 1. Port: 3041 (1 to 65535). Protocol: UDP, TCP.
- Wi-Fi:** Enable Wi-Fi. Mode: Connect to a router, Direct. Authentication: WPA2 (dropdown). SSID: bvfmc gbvv (32 ASCII characters max). Password: 12345678 (8 to 64 ASCII characters). (Reset button).
- IRD Server settings may not be modified while communicating via an IP type connection:** Enable (Edit IRD Server button). Connection type: Ethernet, Wi-Fi. Password: Slade123. Serial number: 134460NEH (Register button).

Buttons at the bottom: Save To File, Load From File, OK, Cancel, Help.

4. Ensure the **Enable DHCP** checkbox is checked. DHCP (Dynamic Host Configuration Protocol) is a standard network protocol for dynamically distributing network configuration parameters, such as IP addresses for interfaces and services. Also take note of the settings in the **Port number** and **Protocol** (UDP or TCP) fields. The default port is 3041.

NOTE: For PEL 102/103, the protocol defaults to UDP and TCP is not supported.

5. Click **OK**. DHCP will automatically assign the instrument an IP address. (This process may take a few moments to complete.) When the IP address is assigned, you can view it by selecting the instrument's name in the navigation frame and clicking the  button to display communication status information in the data frame.



This screen also displays the network port and protocol. Make note of these settings, as well as the IP address; this information will be needed to configure the connection.

6. You can now create a connection to the instrument. To do this, you can either modify the existing USB connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard dialog box, and proceed as instructed in step 8. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.
7. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or (b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.
8. Select the **Ethernet (LAN or Wi-Fi)** radio button and click **Next**. This displays the **Add and Instrument – Network** dialog box.

Add an Instrument Wizard - Network

Specify the IPv4 address and port that the instrument is configured to use

Address:

Port: Protocol: UDP TCP

Example: 3041

 Make sure that your instrument is connected to the network, is powered on and has been assigned an IP address.
The instrument (depending on how it was configured) obtains an IP address from the network (via DHCP) or was assigned one via a USB connection.
Warning: the dynamic address can be regularly renewed by the DHCP server.
If manually assigned an address make sure another device on the same network has not been assigned the same address.
If the PEL is not located on the same network subnet as this computer, you can enter the PEL subnet address and then use the Search button to locate the PEL.

9. Enter the PEL's IP address, protocol, and port number as displayed in the instrument status screen (see step 5 above). When finished, click **Next**.
10. If the connection is successful, a screen appears informing you of this. Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 4: Ethernet Direct (Point-to-Point, APIPA Mode)




Point-to-Point Ethernet communication establishes a direct link between the computer and the instrument via Ethernet cable. To do this, you must be connected to the instrument via a USB connection ([Lesson 1](#)). Then proceed as follows:

1. In the PEL Control Panel, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, and click **Configure** (or click the  icon in the toolbar) to display the Configure Instrument dialog box.
2. Open the **Communication** tab.

A screenshot of the 'Configure' dialog box with the 'Communication' tab selected. The dialog has several sections: 'Bluetooth' with 'Enable Bluetooth' checked, pairing code '0000', name 'PEL 105 -134461NEH', and visibility set to 'Visible'; 'Network' with 'Enable DHCP' checked, IP address '10.1.11.40', subnet mask '255.255.255.0', gateway '10.1.11.1', port '3041', and protocol 'UDP'; 'Wi-Fi' with 'Enable Wi-Fi' checked, mode set to 'Direct', SSID 'bvfmc gbvbv', and password '12345678'; and 'IRD Server settings' with 'Enable' checked, connection type 'Ethernet', password 'Slade123', and serial number '134460NEH'. Buttons for 'Edit', 'Reset', 'Edit IRD Server', 'Register', 'Save To File', 'Load From File', 'OK', 'Cancel', and 'Help' are visible.

3. Ensure the **Enable DHCP** checkbox is checked. If not, select it. Also take note of the settings in the **Port number** field. The default port is 3041. Then click **OK**.
4. Plug one end of an Ethernet cable into the instrument's Ethernet port, and the other end into the computer's Ethernet port. Consult the user documentation that comes with the PEL and/or your computer to locate these ports. The DHCP automatically assigns an IP address to the PEL.

5. Highlight the instrument in the navigation frame and click . This displays the Communication Status screen. Make note of the displayed IP Address.
6. You can now create a connection to the instrument. To do this, you can either modify the existing USB connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard, and proceed as instructed in step 8. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.
7. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or (b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.
8. Select **Point-to-point Ethernet cable (APIPA mode)** and click **Next**. This displays the **Add and Instrument – Network** dialog box:



9. Enter the PEL's IP address, protocol, and port number as displayed in the instrument status screen (see step 5 above). When finished, click **Next**.
10. If the connection is successful, a screen appears informing you of this. Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 5: Wi-Fi Ethernet




This lesson assumes the PEL 105 instrument to which you want to connect has never before been connected to the computer via Wi-Fi.

To set up an Ethernet Wi-Fi connection, you must be connected to the instrument via a USB ([Lesson 1](#)) or Bluetooth ([Lesson 2](#)) connection. You must also have available the following information about your Wi-Fi router:


- SSID of the wireless network
- port number
- password

Consult your network administrator or IT department if you need help obtaining this information. Then proceed as follows:

1. Ensure the computer is connected to the network via Ethernet or Wi-Fi connectivity.
2. Ensure Wi-Fi is enabled on the PEL 105, as indicated by the Wi-Fi indicator on the instrument's front panel. You can enable Wi-Fi through the instrument's front panel interface, as instructed by the instrument's user guide.
3. In the PEL Control Panel, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, and click **Configure** (or click the  icon in the toolbar) to display the Configure Instrument dialog box.
4. Open the **Communication** tab.




5. Ensure **Enable Wi-Fi** is checked. If not, select it.
6. Select **Connect to a router** if it is not already selected.
7. Enter the router's SSID number and password in the **SSID** and **Password** fields.
8. Enter the router's port number. By default, this is 3041.
9. Select the router's communication protocol. By default, this is UDP.
10. Check the setup by pressing the **Test** button. The following dialog box will appear:




During this process, the instrument will attempt to communicate with the router.

If the test is successful, the **Status** field in the Testing Wi-Fi dialog box will change to **Success**.




The dialog box will also display the MAC Address and Wi-Fi IP address the router has assigned to the instrument.

11. Click the  button to display communication status information in the data frame.



Make note of the Wi-Fi address, port, and protocol settings.

12. Find the "communication" icon at bottom right in the computer's taskbar. If the computer has a default Windows 7 layout, this icon will appear as follows:



(If your computer is connected to a LAN network but also has Wi-Fi capability, the icon may appear as ) Left-click the icon to display a list of available wireless networks, identified by their SSIDs.

13. Click the network to which you want to connect. This will be the same SSID entered in step 7 above. Then click **Connect**. If prompted for a password, enter it (see step 7).

14. In the PEL Control Panel, create a connection to the instrument.

If the instrument is not connected, skip the remainder of this step and go to step 15 below.

If the instrument is already connected, you can either modify the existing USB connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard, and proceed as instructed in step 16. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.

15. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or (b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.

16. Select the **Ethernet (LAN or Wi-Fi)** radio button and click **Next**. This displays the **Add and Instrument – Network** dialog box.

17. Enter the router's IP address, protocol, and port number as displayed in the instrument communication status screen (see step 11 above). When finished, click **Next**.

18. If the connection is successful, a screen appears informing you of this. Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 6: Wi-Fi Direct



This lesson assumes the PEL 105 instrument to which you want to connect has never before been connected to the computer via Wi-Fi.

To set up a Wi-Fi direct connection, you must be connected to the instrument via a USB ([Lesson 1](#)) or Bluetooth ([Lesson 2](#)) connection. You must also have available the PEL 105's SSID, port number, and password. Then proceed as follows:

1. Ensure the computer has Wi-Fi capability, either built in or via a Wi-Fi adapter.
2. Ensure Wi-Fi is enabled on the PEL 105, as indicated by the Wi-Fi indicator on the instrument's front panel. You can enable Wi-Fi through the instrument's front panel interface, as instructed by the instrument's user guide.
3. In the PEL Control Panel, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, and click **Configure** (or click the  icon in the toolbar) to display the Configure Instrument dialog box.
4. Open the **Communication** tab.


A screenshot of the 'Configure' dialog box, specifically the 'Communication' tab. The dialog has a title bar with a close button (X) and a tabbed interface with 'General', 'Communication', 'Measurement', 'Current Sensors', 'Recording', and 'Meters'. The 'Communication' tab is active. It contains several sections: 'Bluetooth' with 'Enable Bluetooth' checked, pairing code '0000', name 'PEL 105 -134461NEH', and visibility set to 'Visible'; 'Network' with 'Enable DHCP' checked, IP address '10 . 1 . 11 . 36', subnet mask '255 . 255 . 255 . 0', gateway '10 . 1 . 11 . 1', port '3041', and protocol 'UDP'; 'Wi-Fi' with 'Enable Wi-Fi' checked, mode set to 'Direct', authentication 'WPA2', SSID 'PEL 105-WiFi', and password '12345678'; and 'IRD Server' with 'Enable' checked, connection type 'Ethernet', password '123456789', and serial number '13446 1NEH'. At the bottom are buttons for 'Save To File', 'Load From File', 'OK', 'Cancel', and 'Help'.

5. Ensure **Enable Wi-Fi** is checked. If not, select it.
6. Select **Direct** if it is not already selected.
7. Select the authentication type (**Open** or **WPA2**). If you select WPA2, the **Password** field appears.
8. The PEL 105's SSID appears in the **SSID** field. A default SSID is assigned to the instrument; you can accept the displayed default or enter a new SSID.

If WPA2 is selected as the authentication type, enter the password. (This password will be the Security Key that Windows will request when you connect to the SSID as described in step 10 below.) As with the SSID, a default password is assigned to the instrument; you can accept the displayed password or change it.


Note that both the original SSID and password appear on a tag attached to the instrument when you purchase it.

9. Find the "communication" icon at the bottom right in your computer's taskbar. If the computer has a default Windows 7 layout, this icon will appear as follows:



(If your computer is connected to a LAN network but also has Wi-Fi capability, the icon may appear as )

Left-click the icon to display a list of available SSIDs.




10. Click the SSID to which you want to connect. This will be the same SSID entered in step 8 above. Then click **Connect**. If prompted for a Security Key, enter the password defined in see step 8.
11. In the PEL Control Panel, create a connection to the instrument.

If the instrument is not connected, skip the remainder of this step and go to step 12 below.

If the instrument is already connected, you can either modify the existing USB connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard, and proceed as instructed in step 13. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.

12. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or
(b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.
13. Select the **Wi-Fi direct** radio button and click **Next**. This displays the **Add and Instrument – Network** dialog box, with the network-related fields grayed out.



14. Click **Next**. If the connection is successful, the message **A direct connection has been established with the instrument** appears.
15. Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Lesson 7: IRD Server



You can establish a connection from a computer to a PEL 105 via the IRD (Internet Relay Device) server. This is a computer that facilitates communication between a PEL 105 and a computer running the PEL Control Panel on a private network connected to the internet. This enables you to connect your computer to instruments located on different private networks. The IRD server is hosted by AEMC Instruments and is made available as a free service to all PEL 105 owners.

The PEL 105 offers both an Ethernet and Wi-Fi option for IRD connection. When connected to a network that has internet access, the instrument will automatically register itself with the IRD server using the default serial number and password provided in the instrument.

To configure an IRD connection, your computer must be connected to the instrument via a USB connection ([Lesson 1](#)). Then proceed as follows:

1. In the PEL Control Panel, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, and click **Configure** (or click the  icon in the toolbar) to display the Configure Instrument dialog box.
2. Open the **Communication** tab.


The screenshot shows the 'Configure' dialog box with the 'Communication' tab selected. The 'Bluetooth' section has 'Enable Bluetooth' checked, with a pairing code of 0000 and a name of 'PEL105 -134463NEH'. The 'Network' section has 'Enable DHCP' checked, with an IP address of 192.168.1.111, a subnet mask of 255.255.255.0, and a gateway address of 192.168.1.1. The 'Wi-Fi' section has 'Enable Wi-Fi' checked, with a mode of 'Connect to a router', an SSID of 'NETCON', and a password of 'Dataview7'. The 'IRD Server' section has 'Enable' checked, with a connection type of 'Ethernet', a password of '12345678', and a serial number of '134463NEH'. Buttons for 'Save To File', 'Load From File', 'OK', 'Cancel', and 'Help' are at the bottom.

- In the **IRD Server** section, ensure **Enable** is checked. If not, select it now. When this option is checked, the **Password** and **Serial number** fields appear. (To disable IRD server connection capability, de-select Enable.)
- Connection type** identifies the connection medium (Ethernet or Wi-Fi) through which the PEL 105 communicates with its private network. Ensure this setting matches the connection type used by your instrument.
- To change the password, enter the new password in the **Password** field.
- Edit IRD Server** displays the **IRD Server Settings** dialog box. This lets you change the IRD server URL and port number. In North and South America, the default settings for these are as follows and in normal operation should not be changed:

URL: www.ca-ird.com
 Port number: 80

Outside of the Americas, the default URL is www.ca-ird.eu. (Note that at present both URLs go to the same physical server.)

- If you make any changes to the IRD server settings, you must re-register the instrument with the server. To do this, click the **Register** button. A message box appears displaying the progress of the registration process. If successful, this message appears as follows:




- If the preceding message indicates registration did not complete successfully, review the IRD server settings described in steps 3 through 6 above. Otherwise click **OK**. Then click **OK** a second time to leave the Configure dialog box.

- Highlight the instrument in the navigation frame and click . This displays the **Communication Status** screen. Ensure the **IRD Server Status** setting is **Registration successful**:



- You can now create a connection to the instrument. To do this, you can either modify the existing USB connection, or remove the PEL and re-add it as a new instrument. To modify an existing connection, click the  button to display the Add an Instrument Wizard, and proceed as instructed in step 12. To delete the connection, highlight the instrument in the navigation frame. Then select **Instrument** in the menu bar, select **Remove an Instrument**, and click **Yes** when prompted to confirm the deletion.

11. Either (a) select **Instrument** from the Control Panel menu bar and click **Add an Instrument**, or
(b) click the  icon in the toolbar. Either action opens the **Add an Instrument Wizard** dialog box.
12. Select the **IRD server** radio button and click **Next**. This displays the **Add and Instrument – IRD** dialog box.



Specify the serial number and the password for connection to the IRD server.
By default, this information is available on QR code label of the instrument.


IRD Server URL:

PEL serial number:

Password:

 IRD Server is a server on the Internet used for connection to PEL instruments with private or dynamic IP addresses.
The instrument must be registered with the IRD Server with their serial number and a password.
The instrument must also have access to the Internet to be able to communicate with the IRD server.

13. Check the IRD server URL and ensure it is appropriate for your region. If you need to change this, click the **IRD Server** button and select the URL (www.ca-ird.com or www.ca-ird.eu depending on your region).
14. Enter the PEL 105 serial number and password. The default settings for these are printed on a tag attached to the instrument when you purchase it. You can change the default password (see step 5 above); the serial number cannot be changed. When finished, click **Next**.
15. If the connection is successful, a screen appears informing you of this. If the PEL 105 and your computer are on the same private network, a screen appears as follows:



In this situation, your computer will communicate directly with the instrument without going through the IRD server for the duration of this connection.

Click **Finish** to exit the Add an Instrument Wizard and return to the main Control Panel screen.

Contacting AEMC

For instrument repair and calibration:

Chauvin Arnoux[®], Inc. d.b.a. AEMC[®] Instruments
15 Faraday Drive
Dover, NH 03820 USA
Phone: (800) 945-2362 (Ext. 360)
(603) 749-6434 (Ext. 360)
Fax: (603) 742-2346 or (603) 749-6309
E-mail: repair@aemc.com

(Or contact your authorized distributor.)

For Technical and Sales Assistance:

Chauvin Arnoux[®], Inc. d.b.a. AEMC[®] Instruments
200 Foxborough Boulevard Foxborough, MA 02035 USA
Phone: (800) 343-1391, (508) 698-2115
Fax: (508) 698-2118
E-mail: techsupport@aemc.com
www.aemc.com